


华为云 Paraview 应用服务器网关安装指南

先决条件

- 具有管理权限的华为云账户
- 默认 VPC 或具有公共子网的 VPC
- 必要的区域访问权限和资源。

建筑学



步骤 1：基础设施检查

1. 启动华为云控制台，选择要部署到的地域。至少有一个可访问互联网的默认专有网络 (VPC) 或自定义专有网络 (VPC)。

第 2 步：通过 KooGallery 市场安装

1. 请打开您的浏览器。我们推荐使用 Chrome 浏览器，并[KooGallery 市场](#)。

2. 搜索**Paraview**软件，你会看到一些软件。请点击 **Paraview 应用服务器网关**。
- 3.选择您的安装地区，点击订阅，并同意协议。
4. 按照说明输入 RFS 堆栈名称。以及管理密码。

5.

Create Stack

Select Template

2 Configure Parameters

3 Configure Stack

4 Confirm Configurations

* Stack Name

paraview-pam-stack

The stack name must start with a letter and can contain a maximum of 128 characters, including letters, digits, underscores (_), and hyphens (-). The stack name must be unique.

Description

Paraview pam for HCL

20/255

Configure Parameters

Enter a keyword.

☒ Encrypt some resources based on the template requirements.

Parameter	Value	Type	Description
* admin_password		string	the admin password of ecs.
vpc_cidr	192.168.0.0/16	string	Specifies the range of available subnets in the VPC. The value ranges from 10.0.0.0/8 to 10.255.255.0/24, ...
vpc_subnet_cidr	192.168.10.0/24	string	Specifies the network segment on which the subnet resides. The value must be in CIDR format and within ...
vpc_subnet_gateway_ip	192.168.10.1	string	Specifies the gateway of the subnet. The value must be a valid IP address in the subnet segment. Changin...
* charging_mode	postPaid	string	Specifies the charging mode of the disk. The valid values are as follows:prePaid: the yearly/monthly billing ...
period_unit	month	string	The period unit of the pre-paid purchase.Valid values are month and year. This parameter is mandatory if c...
period	1	number	The period number of the pre-paid purchase. If period_unit is set to month , the value ranges from 1 to 9. If...

6.

Create Stack

Select Template

Configure Parameters

3 Configure Stack

4 Confirm Configurations

Agency

huaweicloud

Select an agency.

How to Create an Agency?

An agency can clearly define RFS's operation permissions (such as creation, update, and deletion) on stack resources. If the agency permissions are insufficient, subsequent operations such as deployment and execution plan creation may fail. [Create Agency on IAM](#)

1 Recommended. If no agency is configured, RFS will have the permissions of the current user for deployment. An agency limits RFS's permissions on cloud service resources, preventing undesired operations caused by incorrect templates or parameters.

Auto-Rollback

☐

If auto-rollback is enabled, the stack automatically rolls back to the previous successful resource status when the operation fails. After the stack is created, you can modify the stack configurations on its details page.

Deletion Protection

☐

Deletion protection prevents the stack from being deleted accidentally. You can modify it on the stack details page.

Firm Configurations

1

Paraview pam for HCL

Description

admin_password	*****	string	the admin password of ecs.
vpc_cidr	192.168.0.0/16	string	Specifies the range of available subnets in the VPC. The value ranges from 10.0.0.0/8 to 10.255.255.0/24, 172.1...
vpc_subnet_cidr	192.168.10.0/24	string	Specifies the network segment on which the subnet resides. The value must be in CIDR format and within the CI...
vpc_subnet_gateway_ip	192.168.10.1	string	Specifies the gateway of the subnet. The value must be a valid IP address in the subnet segment. Changing this...
charging_mode	postPaid	string	Specifies the charging mode of the disk. The valid values are as follows:prePaid: the yearly/monthly billing mode...
period_unit	month	string	The period unit of the pre-paid purchase.Valid values are month and year. This parameter is mandatory if chargi...
period	1	number	The period number of the pre-paid purchase. If period_unit is set to month , the value ranges from 1 to 9. If perio...

Disabled

Directly Deploy Stack

Create Execution Plan

1

To preview your resource billing information, you can create an execution plan.

★ Execution Plan Name

paraview-pam-hcl-stack

Description

Paraview pam for hcl stack

OK

Cancel

8.

paraview-pam-stack

Deploy Update Template/Parameter

Basic Information Resources Outputs Events Template Execution Plans

Deploy

Enter a keyword.

Execution Plan Name/ID	Status	Estimated Price ?	Created	Description	Operation
paraview-pam-hcl-stack e66d9b58-d541-4f8b-a...	Available	View Details	Mar 17, 2025 03:31:25 G...	Paraview pam for hcl...	Deploy Delete

9.

10.完成后，请检查输出以获取登录凭据。

paraview-pam-stack

Deploy Update Template/Parameter

Basic Information Resources Outputs Events Template Execution Plans

Welcome to Paraview PAM standalone Trial edition. Please wait about 5mins then you should able to access http://119.8.186.23 with _sysadmin and Admin.123 credential.

Enter a keyword.

Name	Type	Description
info	string	Welcome to Paraview PAM standalone Trial ed... --

笔记：请耐心等待。安装过程大约需要 5 分钟。请检查 **输出**作为您的应用程序默认凭证。

步骤3：故障排除

1. 开启ECS服务
2. 搜索 paraview-pam-standalone-trial-hcl vm
3. 从操作远程登录

Logging In to a Linux ECS ?

 Ensure that the security groups allow access to port 21, 22, 80, 443, 3389 and ICMP. [View port functions](#)
[Configure security group rules](#) 

CloudShell-based Login (Default Port: 22) Recommended

You can copy and paste commands, manage multiple sessions, and log in to multiple ECSs easily.

Log In

Other Login Modes

CBH-based Login VNC Login

If you have any remote login issues, you can troubleshoot them based on the help documentation. [View FAQs](#) 

4.

Region : ap-southeast-3 Refresh

ECS : paraview-pam-standalone-trial-hcl ...

☒ 119.8.186.23 (EIP) ☐ 192.168.10.235 (Private IP)

Port : 22

User : root ...

Auth-Type : Password-based ...

Password : **Key in your defined admin password**

Session Name : root@119.8.186.23 ...

☒ Open Remote Host Filesystem

Note:

- To ensure the security of the connection, the system will automatically disconnect sessions that have not been active for more than **20 minutes**.
- Please make sure to add inbound rules to allow external network traffic from [CloudShell Proxy Server](#) (SSH default port 22) to be sent to the ECSs in the security group.
- When operations get stuck after remote login, please check the CPU and memory of the machine. Please configure [Cloud Eye](#) to send alarm notifications when abnormal ECS events occur.
- Huawei CloudShell will not save your password, please keep it properly.

Connect Cancel

5.

6.#tail -f /var/log/cloud-init-out.log 获取安装详细信息。